


## **I. Installing the MCI-HUB USB Driver on Windows XP:**

After Plugging the MCI-HUB USB Cable into the computer the following window will appear. Follow the steps below to install the driver for the MCI-HUB USB.


1. Select the “No, not this time” option and press Next.




2. Select “Install from a list or specific location (Advanced)” option and press Next.



3. Select “Search for the best driver in these locations”.
4. Uncheck “Search removable media (floppy, CD-ROM...)”.
5. Check “Include this location in the search:”.
6. Browse to the location of the file “hub\_vista.inf” available with this download.
7. Press “Next”.




8. Press "Finish"




## **II. Installing the MCI-HUB USB Driver on Windows 7:**


If the operating system is Windows 7, the installation of the MCI-HUB driver might not start automatically. Right-click My Computer and choose Properties. The following window appears. On the right side of the window, click on Device Manager.



The MCI-HUB device will appear as Other Devices, right-click it and choose Update Driver Software.



Next, Choose “Browse my computer for driver software” from the Update Driver Software window. Browse to the location of the file “hub\_vista.inf” available with this download.



### **III. Installing the MCI-HUB Control Software:**

This software requires the installation of the .Net Framework version 3.5SP1<sup>1</sup> to operate. First, run “dotnetfx35.exe” to install the framework. Then, run the “setup” file. The “setup” file will automatically download all the required software from the internet before attempting to install the MicroZed Control software.

#### **System Requirements for .Net Framework 3.5 SP1:**

Operating System: Windows Server 2003 and 2008, Windows XP, Windows Vista

Processor Speed: Minimum 400MHz

RAM: Minimum 96MB

Hard Disk Space: Up to 500MB

---

<sup>1</sup> This framework is available with the Windows 7 operating system.